


Savvius Insight Update Procedure

If you connect to your Savvius Insight unit via your Web Browser, the browser will contact the Savvius website to check if there is a newer version of the software. If a new version exists, you will see this message at the top of your browser window:



1. Click "here" to download the latest version of software.
2. You will be taken to the Savvius Support Portal. If you have registered your product, click Login. If you have not, please do so on this page. You must be registered to get software updates.



3. You will then be directed to the .zip file for download to your computer. Save the file.

4. Click on the “Upgrade” button above, and navigate to the .zip archive you have just saved.



5. Open the file. It will automatically be installed. In a few minutes, the unit will reboot itself. When it comes back up, it will be running the new version of software.